

Kurzweil 3000™ for Windows® Version 11 USB Edition Setup

Congratulations on Acquiring the Kurzweil 3000 Version 11 USB Product!

Enjoy Immediate Access without Installing Kurzweil 3000

To run the USB Edition, Kurzweil 3000 Version 11 does not have to be installed on the machine, although it could be. Simply plug the device into a **USB 2.0 port**.

Use Kurzweil 3000 Features and Files Anywhere, Any Time

With the USB Edition, Kurzweil 3000 Version 11 is portable. Work with, save and take your Kurzweil 3000 files and settings with you on the USB device.

Contents of the USB Edition Package, in addition to this Setup Card

USB Device

Kurzweil 3000 Version 11 USB Quick Reference Guide

Certificate of Ownership card containing serial number

Kurzweil Educational Systems Classic Literature CD

Kurzweil Educational Systems Classic Literature CD Guide

System Requirements

USB 2.0 port

Microsoft Windows® 2000, XP, or Vista operating system

512 MB RAM (on Vista: 1 GB RAM)

Pentium® 4 - 2.0 GHz processor

Sound card

Internet connection

Mozilla® Firefox® or Internet Explorer® 6

IMPORTANT PRODUCT INFORMATION

- For the most current product information, including feature availability, see the ReadMe file in the USB Edition device folder.
- Use and store the USB product with care. If you damage the device, lose it, or accidentally remove Kurzweil 3000 files, a replacement is available, contact **Customer Service**:

800.894.5374 (U.S. and Canada); 781.276.0600 (international)



One-Time Activation and Registration of Kurzweil 3000 USB Edition

Activation requires Internet connection, your serial number and product registration.

1. Insert the Kurzweil 3000 USB device into a USB 2.0 port.
2. In the device folder, double-click the **Start** file.
3. In the **Registration** window that opens, click **OK** and select the desired registration option: “**Use Existing Account**” or “**Create New Account.**” Follow the prompts to enter user name, password, serial number and registration information. If you have forgotten your user name and/or password, use Create New Account.
4. **Exit** Kurzweil 3000 and relaunch using the **Start** file in the device folder, then **Exit** again and **Stop** the USB device from the Windows Taskbar before removing it. Your Kurzweil 3000 USB Edition is now activated.

Starting and Exiting the USB Edition

Whenever you use the USB Edition, be sure to do the following:

- Insert the Kurzweil 3000 USB device into a USB 2.0 port.
- In the device folder, double-click the **Start** file.
- When you are finished, **Exit** Kurzweil 3000 and **Stop** the USB device from the Windows Taskbar before removing it.

Note: Removing the device without stopping it may damage your working files; however, no damage will be done to the program files.

Setting Up...

For KESI Virtual Printer: To use this feature, you must first install it from the KESIVP-Installer (for x86 computers) or KESIVP64-Installer (for x64 computers). Both KESIVP installers are in the top level of the USB device folder. Also note that you must have Kurzweil 3000 USB open to use the Virtual Printer.

For Read the Web: You must have Internet access and must first install the kesireader extension file, found in the top level of the USB device folder. Firefox requires separate installation and the extension file copied onto each system.

Kurzweil Educational Systems: www.kurzweiledu.com